


## Steps for typical MD using the AMBER16 GUI

1. Open Linux terminal and type 'perl GUI\_DROIDS\_START.pl' to open GUI
2. specify query and reference PDB files in your DROIDS folder
3. Specify number of production run samples to take (note: should be >30)
4. Check box for solvation method (note: explicit takes longer and uses considerably more memory)
5. Specify the length of heating, equilibration, and each production run (note: energy minimization step is hard coded)
6. Create MD control files
7. Create/check your topology and coordinate files using teLeap
8. Launch MD runs (note: MD runs can be monitored at the main Linux and GPU surveillance terminals. The cpptraj GUI will open upon completion)



## Cpptraj GUI

1. Re-enter PDB and MD control parameters as specified
2. Using GUI, make ccptraj control files, atom info files, atom fluctuation files, and atom correlation files (note: last of these may take awhile)
3. Click 'align structures and prepare files for DROIDS and follow directions on main Linux terminal
4. At two points USCF Chimera will open and you will be prompted to use MatchMaker and Match->Align to create a Clustal (.aln) file as well as to choose the residue from which you want to reference your atom correlations. Simply close Chimera to continue on.
5. DROIDS GUI will open when step 3 and 4 is done.



## DROIDS analysis GUI

1. Enter PDB ID's, length of protein, and number of frames for movies.
2. Choose visualization options for Chimera protein representation, types of motion to analyze, type of K-S test result to view, corresponding color scheme, and method of multiple test correction.
3. Run statistical tests (note: R graphics plots and data files will appear in resulting folder for each analysis)
4. Create chimera attribute file and display these results on static PDB structure in the Chimera viewer
5. Render movies on XYZ axes of the reference PDB and display in DROIDS movie viewer